#### **G202 River Systems**

- I. General Concepts
  - A. The work of running water
    - 1. rivers = "gutters" of continents
    - 2. river work = erosion and transportation
    - 3. driving force: climate and gravity
    - 4. result: sculpting of the landscape
  - B. Fluvial is a generic term that refers to processes pertaining to running surface water
    - 1. Overland flow- general sheet flow of water downslope.
    - 2. Streamflow- channelized concentration of flowing surface water.
  - C. Topographic Considerations
    - 1. Valley- lowlying area that is totally or partially occupied by a stream channel
    - 2. Interfluve- the high land above valley sides that separates adjacent valleys ("between rivers")
      - a. drainage divides hill or ridge areas that separate watersheds
  - D. Running water and erosion
    - 1. Erosion = denudation and stripping of land surface
    - 2. Erosion Processes
      - a. Rain impact or splash erosion
        - (1) controls
          - (a) vegetative cover < rain impact
          - (b) infiltration capacity of ground (permeability)
      - b. Sheet Erosion-
        - (1) overland flow as sheets of water on earth's surface
      - c. Rill Erosion-
        - (1) channel erosion on scale of inches to feet
      - d. Gully Erosion-
        - (1) larger, channelize flows carrying the potential for large amount of sediment.
        - (2) Deforestation and devegetation can result in greatly accelerating the erosion process.

- (a) construction / clearing
- (b) forest fires
- 3. Erosion by stream flow: large-scale channels
  - a. Hydraulic Shear Force- shear force exerted by moving water on sediment particles, has drag effect on moving sediment.
  - b. Abrasion- impact from collisions of pebbles and boulders during stream transport result in physical fragmentation.
  - c. Corrosion: chemical erosion by river water
- E. Sreamflow Parameters: (controlling factors)
  - 1. Discharge of channel: volume of water flowing in channel per unit time (e.g. Gal / min)
    - a. precipitation controlled the amount of discharge in a river is controlled by climate and rainfall patterns
    - b. "Normal Discharge" volume of water is contained well within the river channel boundaries
    - c. "Flood Discharge" volume of water exceeds the carrying capacity of the river channel, and the water overflows onto the surrounding floodplain
  - 2. Velocity- rate of water flow (V=distance / time)
    - a. Controlling factors
      - (1) Gradient of the channel or the longitudinal slope of the stream channel;
        - (a) > Gradient > Velocity, < Gradient < Velocity
      - (2) bed roughness / friction
        - (a) > roughness < velocity, <roughness > velocity
  - 3. Stream Gradient Calculations
    - a. Gradient = rise / run = change is elevation per unit horizontal distance
      - (1) find two contour lines that cross the stream channel
      - (2) determine the elevation difference between the two contour lines by looking at the contour interval
      - (3) measure the channel distance between the two contour lines
      - (4) calculate the gradient
  - 4. Flow path:
    - a. turbulent flow: irregular swirls and eddies in the current path
- F. Transportation of Sediment
  - 1. Dissolved Load: dissolved minerals and salts are carried in water as ions in solution.

- 2. Suspended Load: fine particles of clay and siltare carried in suspension within the body of stream flow without ever touching the streambottom.
  - a. Suspended load tends to comprise the largest portion of total stream load.
- Bedload or Traction Load: sand, gravel, and boulders are commonly transported along thestream bed interface
  - a. saltation- bouncing of particles on channel bottom
  - b. sliding or creep of large particles
- G. Capacity vs. Competence of a Stream
  - 1. Capacity- expression of the potential load that a stream can transport, in vol. of material per unit area.
  - 2. Competence- the largest particle diameter that the stream is capable of transporting given its velocity and shear force
- H. Deposition: sediment placed in storage (NOTE: in my short hand notation "<" is "decrease" and ">" is "increase")
  - 1. Condition of deposition: < gradient of stream bed, < flow velocity, < velocity then < shear force and work capacity, ==== deposition.
  - 2. Sites of deposition by rivers
    - a. floodplains adjacent to river channel
    - b. lakes / reservoirs
    - c. deltas: sediment deposited at the mouth's of rivers
    - d. ocean basins, continental shelf
    - e. "ALLUVIUM": stream deposited debris.
- II. River Morphology
  - A. Plan shape of channel
    - 1. straight channels
    - 2. meandering = sinuous, single channel
    - 3. braided: multiple channels
  - B. Drainage Patterns: often strongly controlled by underlying geology/structural relationships.
    - Dendritic- branch-like pattern with random merging of streams at acute angles.
      Most common pattern, commonly associated with relatively homogenous underlying geology

- 2. Trellis Pattern- rectangular drainage pattern with elongated valleys connected in trellis fashion by cross-cutting water gaps. Commonly found in fold belts with alternating layers of erosionally soft, and resistant rock
- 3. Radial Pattern radially away from center high point, such as a volcano.

#### C. River Landforms

- 1. Channel the main gutter in which the water flows
- 2. Floodplain
  - a. Floodplain- lowlying area adjacent to stream channel that is occasionally inundated with water.
    - (1) technically floods every 2-3 years, according to some river hydrologists
  - b. During overbank conditions, sediments are carried out onto the floodplain, and subsequently deposited upon flood recession.

#### 3. Meander Bend

- a. Stream Meandering: lateral erosion and movement of stream course from side to side
- b. Point Bar
  - (1) Inside Meander Bends: sites of deposition via relative decrease in flow velocity, dropping load on inside bends
- c. Cut bank
  - (1) Outside Meander Bends: sites of erosion via centrifugal force and helical flow pattern, high velocity/high shear zones.
- 4. Natural Levees: ridge of sandy sediment deposited along channel sides during flood event
- 5. Oxbow Lakes: meander loops that are cut off by erosion and isolated as lakes
- 6. Terraces abandoned floodplains
  - a. the floodplains are left stranded high and dry as the river erodes vertically, incising a deeper part of the valley
- 7. Alluvial Fans fan-shaped deposits of river sediments, typically at the mouths of steep mountain canyons
  - a. sediment is deposited as the fluvial energy decreases, when the river exits the mouth of the canyon
  - b. net result: deposition at mouth of canyon in fan shape
- 8. Deltas fan-shaped accumulation of sediments where rivers empty into standing bodies of water
  - a. deltaic deposition results from energy decrease once the river hits the quiet body of water

- b. Lacustrine Deltas (deltas built by rivers flowing into lakes)
- c. Marine Deltas (deltas built by rivers flowing into the ocean)
  - (1) e.g. the Mississippi River delta

# III. Time and Evolution of Fluvial Landscapes

- A. Landscape elevations and topography = function of erosion and uplift through time
  - over time, landscape will undergo denudation unless rejuvenated by uplift and / or tectonic process

#### B. Base Level Of River

- 1. Ultimate level to which river will erode = sea level
- 2. Surface above base level = site of erosion
- 3. Surface below base level = site of deposition

## C. Landscape Maturity

- 1. Youth: straight, steep and rapid
- 2. Mature: sinuous, moderate slopes
- 3. Old Age: very flat topography, oxbow lakes, highly meandering


#### IV. Watershed Analysis


- A. Watershed = a unit of land that collects all the surface drainage for a given stream or river
  - 1. Defined on the basis of drainage divides or ridges that separate surface flow into each adjoining watershed

## B. Water Budgets

- Calculations of water volumes in the form of precipitation and surface runoff into streams
- 2. Important for landuse / water resource issues


# Hydrologic Cycle and Fluvial Systems






Point Bars / Cut Banks


# Alluvial Fans






Floodplain Evolution

T60



Strahler Stream Orders



**Drainage Patterns**